



Duvet-in-a-Day Pillows

“Duvet-in-a-Day” patterned in the Oct/Nov 2010 issue of QUILT Magazine

Web Bonus pattern for pillows
by Stephanie Brandenburg

From the Lulu collection by Camelot Cottons,
www.camelotcottons.com

Small Round Pillow with Piping

Materials:

1/3 yard of a pillow fabric
1-1/2 yards of 6/32" cording
1/2 yard of a piping fabric
Polyester fiberfil for stuffing

Cutting:

From the pillow fabric:
(2) 11" diameter circles


From the piping fabric:
32" length of 1-3/4" wide bias strip

Sewing Directions:


1. Place the cording in the center of your bias strip and wrap the bias strip around the cording, matching the raw edges.
2. Place the zipper foot of your machine right along the edge of the cording. Stitch seam allowances together to encase the cording.



3. Place the piping onto the right side of your pillow front, with the cording to the inside of the seam allowance, matching the raw edges. Using your zipper foot and 1/2" seam allowance, stitch the piping in place, making sure your stitches cover the piping stitches. Clip the curves of the piping fabric if needed. When you start stitching, leave the first 1/2" unsewn. To end the piping, trim the cording so that the ends of the cording butt up against each other. Fold under the extra fabric 1/2" to enclose the beginning and the end of the piping (cut off excess if needed). Stitch end of piping fabric in place.



4. Place pillow front and pillow back right sides together. Pin together. Using 1/2" seam allowance, stitch all the way around the pillow, leaving an opening to turn the pillow right side out. When you stitch, make sure you stitch along the seam line from when you added the piping, so that you will not see the piping stitches on the right side of your pillow. Zig zag stitch or use your serger to finish the seam allowance. Turn pillow right side out and press. Stuff with polyester fiberfill to your desired firmness. Slip stitch opening closed.



12" Pillow with Piping

Materials:

1/2 yard of a pillow fabric
2 yards of 6/32" cording
1/2 yard of a piping fabric
12" pillow form

Cutting:

From the pillow fabric:
(1) 13-1/2" square
(2) 10" x 13-1/2" pieces

From the piping fabric:
52" length of 1-3/4" wide bias strip

Sewing Directions:

1. Press 1/4" under on a 13-1/2" side of (1) 10" x 13-1/2" pillow piece. Press 1/4" under again. Stitch down the folded under seam along the loose edge. Repeat on the second back piece.


2. Place the cording in the center of your bias strip and wrap the bias strip around the cording, matching the raw edges. Place the zipper foot of your machine right along the edge of the cording. Stitch seam allowances together to encase the cording.



3. Place the piping onto the right side of your pillow front, with the cording to the inside of the seam allowance, matching the raw edges. Using your zipper foot and 1/2" seam allowance, stitch the piping in place, making sure your stitches cover the piping stitches. Clip the corners of the piping fabric if needed. When you start stitching, leave the first 1/2" unsewn. To end the piping, trim the cording so that the ends of the cording butt up against each other. Fold under the extra fabric 1/2" to enclose the beginning and the end of the piping (cut off excess if needed). Stitch end of piping fabric in place.



4. Lay the front panel and the two back panels with right sides together, making sure to line up your raw edges and corners. The two back panels will overlap each other about 2". Pin in place. Working on the wrong side of the front so you can see the piping stitches, stitch the front and back together, using a 1/2" seam allowance. Zig zag stitch or use your serger to finish the seam allowance. Turn pillow right side out. Press pillow. Insert pillow form into the pillowcase.



14" x 22" Pillow with Piping

Materials:

1 yard of a pillow fabric
2-1/2 yards of 6/32" cording
1/2 yard of a piping fabric
Polyester fiberfill

Cutting:

From the pillow fabric:
(2) 15" x 23" pieces

From the piping fabric:
78" length of 1-3/4" wide bias strip

Sewing Directions:


1. Place the cording in the center of your bias strip and wrap the bias strip around the cording, matching the raw edges. Place the zipper foot of your machine right along the edge of the cording. Stitch seam allowances together to encase the cording.



2. Place the piping onto the right side of your pillow front, with the cording to the inside of the seam allowance, matching the raw edges. Using your zipper foot and 1/2" seam allowance, stitch the piping in place, making sure your stitches cover the piping stitches. Clip the corners of the piping fabric if needed. When you start stitching, leave the first 1/2" unsewn. To end the piping, trim the cording so that the ends of the cording butt up against each other. Fold under the extra fabric 1/2" to enclose the beginning and the end of the piping (cut off excess if needed). Stitch end of piping fabric in place.



4. Place pillow front and pillow back right sides together. Pin together. Using 1/2" seam allowance, stitch all the way around the pillow, leaving an opening to turn the pillow right side out. When you stitch, make sure you stitch along the seam line from when you added the piping, so that you will not see the piping stitches on the right side of your pillow. Zig zag stitch or use your serger to finish the seam allowance. Turn pillow right side out and press. Stuff with polyester fiberfill to your desired firmness. Slip stitch opening closed.



26" Square Pillow with Piping

Materials:

1/2 yard of a pillow fabric for front
1/2 yard of pillow fabric for back
3-1/2 yards of 6/32" cording
1/2 yard of a piping fabric
26" square pillow form
Fusible interfacing

Cutting:

From the pillow front fabric:
(1) 27-1/2" square

From the pillow back fabric:
(2) 18" x 27-1/2" pieces


From the piping fabric:
110" length of 1-3/4" wide bias strip

Sewing Directions:

1. Press 1/4" under on a 27-1/2" side of (1) 18" x 27-1/2" pillow back piece. Press 1/4" under again. Stitch down the folded under seam along the loose edge. Repeat on the second back piece.
2. Place the cording in the center of your bias strip and wrap the bias strip around the cording, matching the raw edges. Place the zipper foot of your machine right along the edge of the cording. Stitch seam allowances together to encase the cording.



3. Place the piping onto the right side of your pillow front, with the cording to the inside of the seam allowance, matching the raw edges. Using your zipper foot and 1/2" seam allowance, stitch the piping in place, making sure your stitches cover the piping stitches. Clip the corners of the piping fabric if needed. When you start stitching, leave the first 1/2" unsewn. To end the piping, trim the cording so that the ends of the cording butt up against each other. Fold under the extra fabric 1/2" to enclose the beginning and the end of the piping (cut off excess if needed). Stitch end of piping fabric in place.



4. Lay the front panel and the two back panels with right sides together, making sure to line up your raw edges and corners. The two back panels will overlap each other about 4". Pin in place. Working on the wrong side of the front so you can see the piping stitches, stitch the front and back together, using a 1/2" seam allowance. Zig zag stitch or use your serger to finish the seam allowance. Turn pillow right side out. Press pillow. Insert pillow form into the pillowcase.

